

Dizzion C3

Dizzion Frame now supports Dizzion C3 as an authentication provider, allowing administrators to use the same credentials they already use for support.dizzion.com and c3.dizzion.com to access Frame. By enabling Dizzion C3 authentication, users can seamlessly log in without managing multiple credentials, improving security and streamlining access. This guide will walk you through the steps to enable Dizzion C3 as an authentication provider.

Prerequisites


Before enabling Dizzion C3 authentication for Frame, ensure the following:

- You have the **Frame Customer Admin role in Dizzion C3** (contact your [Dizzion Customer Success Manager](#) if needed)
- You have administrator access to the Frame Admin Console to configure authentication settings.
- Your Frame organization/account is set up and active.\n- Users have valid **Dizzion C3 credentials** to authenticate.\n\n



By default, any user with the **Frame Customer Admin role** assigned within Dizzion C3 will automatically be assigned the **Customer Administrator role** within Frame.

Configuration

1. Log in to Frame and navigate to **Users > Authentication** from either the Organization or Account level of the Frame Console. (More details around authentication based on tenant hierarchy can be found [here](#).)
2. Enable **Dizzion C3** on this page (under the **Authentication** tab). Click **Save** in the upper right corner of the page.



3. Once enabled, **Dizzion C3** will appear as a sign-in option on the Frame login page.



4. Users can now simply click on the **Sign in with Dizzion C3** to be redirected to the Dizzion C3 authentication portal. If authentication is successful, you will be redirected back to Frame with access granted.




Welcome to Cosmos Control Center

Email Address

Next

DIZZION 

Information system usage may be monitored, recorded, and subject to audit. Unauthorized use of the information system is prohibited and subject to criminal and civil penalties. Use of the information system indicates consent to monitoring and recording.



Users with the appropriate role can now log in using their Dizzion C3 credentials.

Accessing Frame from the Dizzion C3 Portal

Administrators with the **Frame Customer Admin** role can also log in to Frame directly from the Dizzion C3 portal by following the steps below:

1. Navigate to the [Dizzion C3 Portal](#).
2. Enter your email address and click **Next**.
3. Enter your password and click **Sign In**.



test.admin@dizzion.com

Sign in with your C3 Account


Password

[Forgot Password?](#)


Sign In

[Restart Login](#)

DIZZION 



4. Click on "Click here to launch Frame" to be redirected.



5. A new browser tab will open, and you will be automatically redirected to Frame.

Additional Resources

Enabling this feature allows user access to be managed through Dizzion's C3 Platform. If you wish to modify user access to the platform, you must do so via C3. More detailed information around C3 user management can be found in our [C3 Administration documentation](#).

Revision #4

Created 1 October 2025 04:49:35

Updated 13 January 2026 12:03:19 by Nikola Savic