

Register Workloads (Early Access)

Overview

The **Register Workloads feature** lets customers bring existing virtual machines or workloads into the Dizzion Frame platform as persistent desktops without recreating or migrating resources. It supports all Dizzion-approved infrastructures including AWS, Azure, Google Cloud, IBM Cloud, and Nutanix AHV. This feature is ideal for migration scenarios from e.g. Citrix, Microsoft, or Omnissa, enabling smooth A/B and acceptance testing alongside existing environments.

Prerequisites

Before registering workloads, ensure the following:

1. The cloud account containing the workloads has been imported into Frame using the standard cloud account creation procedure. See: [Add Cloud Account](#) for more information.
2. This feature only works for Windows Operating Systems
3. The workloads are accessible over the network and can be reached using VNC, Microsoft RDP, Citrix HDX, Omnissa (VMware) Blast, or any other supported connection protocol.
4. For manual installation, you need administrative privileges on the workload VMs to install the Frame Guest Agent. For unattended installation, make sure the Frame Agent Setup Tool (FAST) is downloaded and setup for automated installation.
5. Workloads must have outbound network connectivity on TCP port 443 (HTTPS) to access the registration URL, which is provided in the setup instructions below.
6. All networking requirements must be met as described in the reference documentation [here](#) .

Workflow:

Step 1. – Create a Persistent Desktop Account

Here are more details about [Persistent Desktops](#)

Step 2 - Register Workloads from console by:

Go to the VMs page and select the “Register Workloads.”

A screenshot of a computerAI-generated content may be incorrect.

Specify the number of workloads you want to import into a persistent desktop pool.

A white rectangular object with a black lineAI-generated content may be incorrect.a registration code with an expiration time, along with the backplane URL will be displayed.

A screenshot of a computerAI-generated content may be incorrect.

New objects appear on the VMs page, serving as placeholders until the actual virtual machines register. If the registration code expires, refresh the page to generate a new one.

A screenshot of a computerAI-generated content may be incorrect.

Step 3 - Install Frame Guest Agent on Workloads

Manual installation

On each workload VM, connect using VNC, Microsoft RDP, Citrix HDX, Omnissa (VMware) Blast, or another preferred protocol, then run the Frame Agent Setup Tool (FAST) with the registration parameters.

Download the installer, the Frame Agent Setup Tool (FAST)

<https://files.difr.com/>

Run the registration command

```
frameagentsetuptool.exe install frameimage registrationcode=<code> registrationurl=<url>
```

Replace <code> and <url> with the values generated in Step 2 of the Workflow.

Registration via UI:

A screenshot of a computerAI-generated content may be incorrect.

Use `<code>` and `<url>` with the values generated in Step 2 of the Workflow.

Unattended Installation

For larger environments, the Frame Agent Setup Tool (FAST) can be deployed automatically using standard management tools.

Recommended Methods

- PowerShell Script: Run locally or remotely or distribute via GPO.
- Intune / Endpoint Manager: Package FAST as a Win32 app and assign to devices.
- Cloud Startup Scripts: Add the command to Azure Custom Script, AWS User Data, or GCP startup metadata for automatic registration at boot.
- Use any third-party deployment tool of your choice.

Tips

- Always use the latest installer.
- Test with one VM before broad rollout.
- Ensure outbound connectivity to the registration URL.

Step 4 - Automatic Registration

After running the command, the Frame Guest Agent automatically registers the workload. Each workload then appears in the Persistent Desktop Production Pool as an unassigned persistent desktop.

Step 5 - Manual Assignment

Once the workloads are visible on the VMs page, manually assign each imported persistent desktop to the corresponding user through the Frame Console.

Step 6 – Create a Launchpad

Set up a desktop [Launchpad](#) for end users to access these VMs, if it doesn't already exist and [configure SAML2 permissions](#).

That's it. Workloads created outside of Frame are now part of the persistent desktop pool, with no functional limitations after registration as all standard operations are supported.

Revision #10

Created 17 October 2025 07:28:42 by Stefan Gajic

Updated 21 January 2026 08:38:55 by Nikola Savic